

MTS Software Change Log

MTS1000.2.1.0	Status: Active	Release Date: 04/06/2018
Update Includes	This release adds the following new features: <ul style="list-style-type: none"> • Changed: Last hour has been changed to last 24 hour. • Changed: Emergency Cool can now be activated based on return air temperature when the LC is not online. • Added: Unit status to communication lines for use at LC6000. • Added: Time delay to evaporator freeze alarm 	
Know Issues	<ul style="list-style-type: none"> • None 	
Software Compatibility	<ul style="list-style-type: none"> • LCS6000.2.1.0 	
Hardware Compatibility	<ul style="list-style-type: none"> • W***AP 	

MTS1000.2.0.0	Status: Active	Release Date: 01/31/2018
Update Includes	This release adds the following new features: <ul style="list-style-type: none"> • Added: control of reheat valve during dehumidification call from LC • Added: Electric reheat option during dehumidification call from LC • Changed: Unit status message is much more detailed to indicate unit operation to user. • Changed: Run test is now more reliable and includes step for Reheat valve on dehumidification models. • Fix: thTune no longer causes memory retention error • Changed: New Modbus standard was implemented to allow easier integration of future products and standardize the equipment communication. • Removed: No longer an option to configure a wall unit's mode. This has been replaced by the new staging sequence in the LC6000. 	
Know Issues	<ul style="list-style-type: none"> • 	
Software Compatibility	<ul style="list-style-type: none"> • LCS6000.2.0.0 	
Hardware Compatibility	<ul style="list-style-type: none"> • W***AP 	

MTS1000.1.0.9	Status: Discontinued 04/06/2018	Release Date:	10/01/2017
Update Includes	This release adds the following new features: <ul style="list-style-type: none"> • thTune functionality • Runaway Heat Protection • High Return Air Alarm • Password Reset via date encrypted rolling password • Continuous Blower – turn on immediately in standby, turn of when unit commanded off by keypad • Run-Test – disable run test when off by keypad, run test operation with blank off plate • Alarms – add sensor ok check to high/low temperature alarm • Display – Change “Controller Address:” to “Unit Address:” 		
Know Issues	<ul style="list-style-type: none"> • Memory Retention Error occurs causing Alarm log to fill rapidly 		
Software Compatibility	<ul style="list-style-type: none"> • LCS6000.1.1.0 		
Hardware Compatibility	<ul style="list-style-type: none"> • W***AP 		

MTS1000.1.0.8	Status: Discontinued 10/01/2017	Release Date:	02/17/2017
Update Includes	This release adds the following new features: <ul style="list-style-type: none"> • Fixed issue with economizer enthalpy and temp/hum not operating • Changed freeze stat alarm to auto reset instead of latching • Changed heating differentials and relabeled all differentials to on and off • Fixed issue where continuous blower would override smoke alarm shutdown • Fixed issue where LC smoke shutdown was overridden by continuous blower 		
Know Issues	<ul style="list-style-type: none"> • Continuous blower operates when unit is turned off from the menu 		
Software Compatibility	<ul style="list-style-type: none"> • LCS6000.1.0.8 • LCS6000.1.1.0 		
Hardware Compatibility	<ul style="list-style-type: none"> • W***AP 		

MTS1000.1.0.0	Status: Discontinued 02/17/2018	Release Date:	8/18/2016
Update Includes	This release adds the following new features: <ul style="list-style-type: none"> • Initial Release 		
Know Issues	<ul style="list-style-type: none"> • Economizer does not operate in temperature/humidity or enthalpy mode • Freeze stat alarm requires user reset • Continuous Blower will override smoke shutdown sequence 		
Software Compatibility	<ul style="list-style-type: none"> • LCS6000.1.0.8 • LCS6000.1.1.0 		
Hardware Compatibility	<ul style="list-style-type: none"> • W***AP 		



MULTI-TEC Series

Software Status

Active	Current version of software.
Available	Stable version available from website or Bard Technical Service.
Discontinued	Software version no longer supported, recommend updating to the Active version.